

# EMDK for .NET v2.4 update for MT2000 with firmware version 01.25.22

[Part #: ]

---

## Contents

- [Description](#)
  - [Device Compatibility](#)
  - [Release Notes](#)
  - [Components](#)
  - [Installation](#)
  - [Notes](#)
  - [Late Additions](#)
- 

## 1 Description

This update for EMDK for .NET is provided for development of the .NET application that uses Symbol.MT2000.ScannerServices.dll to work with MT2000 series scanner with firmware version 01.25.22.

[Back to Top](#)

---

## 2 Device Compatibility

MT2000

[Back to Top](#)

---

## 3 Release Notes

### Version 1.0.4.0

Updated “Symbol.MT2000.ScannerServices.dll” version 1.0.4.0 compatible with MT2000 with firmware version 01.25.22.

[Back to Top](#)

---

## 4 Components

Component	Location
Symbol.MT2000.ScannerServices.dll	C:\Program Files\ EMDK for .NET\v2.4\SDK\Smart Devices

[Back to Top](#)

---

## 5 Installation

### Development PC

1. Close any instances of Visual Studio 2005
2. Install EMDK for .NET v2.4
3. Locate the EMDK Install folder. The default is “C:\Program Files\ EMDK for .NET\”.
4. Manually copy files from the update package to the development PC replacing the existing files.

[Back to Top](#)

---

## 6 Notes

[Back to Top](#)

---

## 7 Late Additions

[Back to Top](#)

---

Last revised: October 05, 2011